# **NSP GUIDE** Deactivation of TEKLYNX Products with NSP

This guide is only applicable for:

- CODESOFT 2012
- LABELVIEW 2012
- LABEL ARCHIVE 2012
- LABEL MATRIX 2012
- PRINT MODULE 2012
- SENTINEL 2012



## Deactivation of TEKLYNX products with NSP

This document presents the new software protection (NSP) wizards used to deactivate a software key protected license.

Table of contents	Page
A. Deactivate a license	<u>3</u>
1. Deactivate online	<u>4</u>
2. Deactivate online with a proxy	<u>4</u>
3. Deactivate using a USB key	<u>8</u>
4. Deactivate using our web site	<u>10</u>
5. Deactivate using a smartphone	<u>12</u>

## A. Deactivate a license 🚳

Launch the License Manager:

- For Windows versions older than Windows 8: Start menu > Programs > TEKLYNX Software name 2012 > Software name 2012 License Manager.
- For Windows 8 users: Access the search tool. To access and use the search tool, open the Charms menu by pressing Win [Windows key] + C on your keyboard or by swiping in the top-right or bottom-right corner. Once the Charms menu pops open, click/tap the Search button. Type License Manager.

With the **License Manager**, you can upgrade a license, transfer a license to another computer and also deactivate a license.

License Manager	
4	
	Current license (expired): NSP2-820 - COOT COOT COOTS (Contract State at Abs
	Upgrade software license
	Deactivate software license
TEKLYNX	Transfer software license You want to deactivate the software on this computer in order to reactivate on another computer. You have 2 license transfer token(s) left.
_	📑 Back 💽 Next 🚺 Exit

Five modes are available to deactivate your software license: **Deactivate online**, **Deactivate online through a proxy**, **Using a USB key**, **Using our website**, **Using a smartphone**.

• Deactivate online

If you have an Internet connection on the computer where the software is installed, online deactivation is automatically selected.

• **Deactivate online through a proxy** Some enterprise networks are protected by a proxy server. In this case, you have to configure the connection through a proxy.

#### • Using a USB key

If you do not have an Internet connection on the computer where the software is

installed but you have access to another computer with an Internet connection, you can deactivate the product by clicking **Using a USB key**.

#### • Using our website

You (or someone else) with an Internet connection can connect to our website to deactivate the license.

#### • Using a smartphone

A barcode scanner application is required to read the barcode which allows you to deactivate your software using a smartphone. You can download this from your application store / market. This deactivation mode uses an Internet connection on your smartphone.

## 1. Deactivate online 🚳

If you have an Internet connection when you click on **Deactivate software license**, the following message appears:

⚠	You will no longer be able to use your software on this machine. Do you want to continue?
	OK Cancel

If you click **OK**, the license is deactivated.


#### 2. Deactivate online with proxy 🚳

Some enterprise networks are protected by a proxy server.

1. When you click on **Deactivate software license**, the following message appears. Click **OK**.

⚠	You will no longer be able to use your software on this machine. Do you want to continue?
	OK Cancel

2. Select Online through a proxy.



3. If the proxy analysis or connection through proxy fails, the wizard lists the operations to do. Passing the cursor over a failed item, a tooltip indicates what the problem is.

Activation Wizard - Testing con	nection	×
L L	Testing connection to licensing server	
	Connecting to the server	Failure
~	Connecting to the server via proxy	Failure
	This license requires an Internet connection. firewall settings or configure your proxy if you I the Settings button.	
TEKLYNX		Save Save
Settings	← Back → Next	O Exit

- Connecting to the server Failure: Please check that you have an Internet connection and that ports 80 and 443 are open in your firewall to connect to our server.
- Connecting to the server via proxy Failure: No valid proxy detected. Please configure your proxy if you have one by clicking Settings.

NSP Settings	×
Proxy	<ul> <li>Use Proxy Server</li> <li>Proxies with authentication are not supported.</li> <li>Use proxy defined in Windows Internet Options</li> </ul>
Alerts	Image: Secondary Server Test       ✓       Success         Secondary Server Test       ✓       Success         Primary Server Test       ✓       Success         Primary Server Test       ✓       Success         Image: Secondary Server Test       ✓       Success
	OK Annuler Appliquer

3. Check **Use Proxy Server**. Define the valid IP address of your proxy server in the **Custom** field and click the **Test** button to test your connection.

If an error is displayed, a message will indicate the problem and the process to do to resolve it.

If you do not have an Internet connection on the computer where the software is installed, click the **Cancel** button in the **Settings** dialog box and click the **Back** button in the **Deactivation Wizard – Testing connection** to select another deactivation mode.

4. If the connection test is successful, click Next.


A message informs you that the product has been deactivated.

# 3. Using a USB key 🚳


1. When you click on **Deactivate software license**, the following message appears. Click **OK**.



2. Select Using a USB key.



3. Select the media to be used for deactivation (USB key, external hard disk, network drives...).




The list is empty if no removable media is detected. The list is refreshed as soon as a new removable media is plugged to the computer.

- 4. Click on **Next**. The license is deactivated and the files used to recover your token will be copied onto the selected media.
- 5. Unplug the removable media.
- 6. Plug the removable media into the computer connected to Internet.
- 7. Double-click **USBWizard.exe** (which can be found on the root of the media). This will start the wizard.
- 8. Select the license(s) to deactivate and click on Next.
- 9. You recover your activation token when your deactivation process is successful.
- 10. Unplug the removable media from this computer.
- 11. Click on Finish.

### 4. Using our website 🚳



1. Select Using our website.



 The link provided in this screen (<u>http://www.teklynx.eu/nsp/</u>) can be reached from a different computer with Internet access. You or someone else with an Internet connection can connect to our website to complete the deactivation. The Serial Number and Password (provided with the product) and the User Code (displayed in the wizard) will be required in order to use this service.

License Manager		$\mathbf{X}$
41		
	The link provided below internet access. You will in order to use this servio	can be reached from a different computer with need the Serial Number, Password and User Code e.
	http://www.teklynx.eu/r	<u>sp/</u>
	User Code	CODER XUMER ÉSTERIORIZU UDRED E KOMU BATCHECKZOUNO DOMINITARIO SUMA CIDIO D
тексунск		
		Back Next O Exit

3. The link <u>http://www.teklynx.eu/nsp/</u> allows you to display the following website page:

Welcome to the TEKL					
		tivations web site which al	lows you to re	egister and activate TE	KLYNX software.
Fill-in the following fields	. All fields are requ	vired.			
	Required		Required		Required
First Name	Required	Last Name	Reguireu	Company Name	Required
Email	Required	Phone	Required	Address	Required
City	Required	Postal Code	Required	Country	Required
				Select Country	~
What industry is your business in ?	Required	l accept to receive information and special offers from Teklynx or its partners	Required		
- Choose one -	*				
		O Yes 💿 No			

- 4. Input the license user's information in the **User Registration** form displayed on our website.
- 5. Click on **Submit**.
- 6. A message informs you that the product has been deactivated.

### 5. Using a smartphone 🚳

A barcode scanner application is required to read the barcode which allows you to deactivate your software using a smartphone. You can download this from you application store / market. This deactivation mode uses an Internet connection on your smartphone.



1. Select Using a smartphone.

- 2. A barcode is displayed in the wizard. Move the cursor over the barcode to zoom in.
- 3. Open your barcode scanner application on your smartphone.
- 4. Scan the barcode with your smartphone.
- 5. Click on **Continue** or open the browser on the phone.
- 6. The Software Activation website is displayed. This allows you to register and deactivate your software. All fields must be filled in.

II 🤝		14:5			\$ •
T	EKLY	NX Softwa	are A	ctivations	5
www.tek	lynx.e	eu/nsp/	Ċ	Goog	gle
AIDC SOFTWARE				TR	LYNOX (1)
Welcame to the TBK Fill in the Johanny (M		uthrations web die which gehad	alicet you to	register and activite T	ERLINK Lativary.
Toti Name	Sector	Last Name	(Arrest)	Camping Blane	Annal
Eval	9464	Flain	1		1944
184	(Sec.)	Postal Lade	form		Anna a
What balanty is your balance is 7	Saint S		(two)		
terit turke	-	Paramet		Gar Lab	No.
<		+		<u></u>	G

- 7. Click on Submit.
- 8. A message informs you that the product has been deactivated.